Email Configuration Guide POP3 and IMAP

Apple Mail

Version 2.4

1	R	equired Settings	. 3
2	S	erver Settings	. 3
3	Setting up your email account		. 4
	3.1	Step 1	. 4
	3.2	Step 2	. 4
	3.3	Step 3	. 5
	3.4	Step 4	. 5
	3.5	Step 5	. 6
	3.6	Step 6	. 6
4	S	upport	. 8

1 Required Settings

Most email programs that support the POP/IMAP and SMTP email standards for sending and receiving email use the following five primary settings.

- 1. Username You must enter your complete email address. (Example: username@yourdomain.com)
- 2. Password This is the same password that you use to login to Web Mail.
- 3. Incoming Mail Server
- 4. Outgoing Mail Server (SMTP)
- 5. Outgoing Mail Server (SMTP) Authentication

In order to send email, you must set your email software to use authentication when connecting to the outgoing mail server. If your email software asks you to enter a username and password, enter the same username and password that you entered in settings one and two above.

2 Server Settings

Server Type	Server Name	Port
POP	pop.yourdomain.net	110
POP with SSL	pop.yourdomain.net	995
IMAP	imap.yourdomain.net	143
IMAP with SSL	imap.yourdomain.net	993
SMTP	smtp.yourdomain.net	25
SMTP alternative port	smtp.yourdomain.net	2525
SMTP with SSL	smtp.yourdomain.net	465

3 Setting up your email account

3.1 Step 1

- 1. Launch Mail (First time users will receive the Welcome to Mail window)
- 2. Click Continue

000	New Account
COMERCING	Welcome to Mail You'll be guided through the necessary steps to set up your mail account.
	To get started, click Continue.
(Cancel

3.2 Step 2

- 1. Account type: POP
- 2. Account Description: POP Account
- 3. Full Name: Enter First and Last name
- 4. Email address: enter email address
- 5. Continue

000	New Acco	punt
	General Information	
mm	Account Type:	POP 🛟
ST W	Account Description:	POP Account
5 5	Full Name:	
3	Email Address:	tester@yourdomain.com
0-10		
- 11 <i>6</i> a -		
CURFETINIO		
CALING		
?	Cancel	Continue

3.3 Step 3

- 1. Incoming Mail Server: pop.yourdomain.net
- 2. User Name: Enter full email address
- 3. Password: Your password to the Email address
- 4. Continue

000	New Account	
	Incoming Mail Server	
mm	Incoming Mail Server:	pop.yourdomain.net Example: mail.example.com
3	User Name:	tester
2 1	Password:	
CIPERING		
?	Cancel	Go Back Continue

3.4 Step 4

- 1. Authentication : Select **Password**
- 2. Check Use secure Sockets Layer (SSL) if required by your ISP or email provider
- 3. Continue.

0 🖯 🔿	New Account	
State Concerned	Incoming Mail Security Use Secure Sockets Authentication: Passw	Layer (SSL) vord
?	Cancel	Go Back Continue

3.5 Step 5

- 1. Outgoing Mail Server: smtp.yourdomain.net
- 2. User Name: Your full email address
- 3. Password: Your password to the Email address
- 4. Check the box for Use Authentication
- 5. Continue

3.6 Step 6

- 1. Confirm your settings in the Account Summary window
- 2. Continue



Step 7 Your Account has been created! Click **Done** to close the setup wizard.

000	New Account
A LONG	Conclusion A new account has been created. You can make changes to your account information in Account Preferences. Import Mailboxes Create Another Account
(Cancel Go Back Done

Changing Default SMTP Port

If your ISP is blocking port 25 (default SMTP Port) you will be required to use your domain's alternative SMTP port 2525. Open Mail. In the menu bar, choose Mail -> Preferences, and then click Accounts.

From the Accounts list, select your account, and then click the Account Information tab.

From the Outgoing Mail Server (SMTP) dropdown menu, choose your outgoing server. Click the Server Settings button.

Change the "Server port" to 2525.



Click on OK to save your settings.

4 Support

Contact your system administrator to provide you with assistance for your email service.